

Stratos-E461

ChangeLog Firmware History

Knick Elektronische Messgeräte GmbH & Co. KG

www.knick.de

Content

Content.....	2
1 Firmware versions	2
1.1 Version 1.2.1.....	2
1.2 Version 1.3.0.....	2
1.3 Version 1.3.1.....	2
1.4 Version 1.4.0.....	2

1 Firmware versions

1.1 Version 1.2.1

Change: Nominal zero point for pH sensors

Range extension: -19.99...19.99 pH

New: Trace measurement for oxygen sensor SE740

1.2 Version 1.3.0

Change: Display of the cell constant of conductivity sensors extended to up to 5 decimal places

1.3 Version 1.3.1

New: Live measured values in the toolbar

Change: Extension of the setting range for the polarization voltage of analogue oxygen sensors

The value range has been extended from -1000...-400 mV to -1000...0 mV.

1.4 Version 1.4.0

Bugfix: Messages P065 and D064 “Sensoface sad cal. timer” changed from class failure to maintenance Requirement

Change: Input option flush interval changed from 0.1 h to 0.01 h