

Portavo-904

ChangeLog
Firmware History

Knick Elektronische Messgeräte GmbH & Co. KG

www.knick.de

Content

Content.....	2
1 Versions-History	2
1.1 Version 1.4.0.....	2

1 Versions-History

1.1 Version 1.4.0

Bugfix: Calibration date for redox calibrations in Memosens pH/Redox sensor

New: Oxygen measurement in gases

New: Message "Time and date incorrect" if the device date is older than the calibration date in the Memosens sensor.

Change: Calculation of resistivity with temperature-compensated conductivity

Change: Limit of the measurand TDS extended to 0...5000 mg/l

Change: Date format selection text in menu from MM.DD.YY to MM.DD.YY

New: Date/time can be displayed in the third line of the measured value display

New: Specific resistance of conductivity measurements can be recorded with the logger

Change: Setting range logger type difference extended to a resolution of 1 uS/cm

New: Rescue TAN for resetting access codes