

## **Stratos-E471**

### **ChangeLog Firmware History**

**Knick Elektronische Messgeräte GmbH & Co. KG**

[www.knick.de](http://www.knick.de)

## Content

Content.....	2
1 Firmware versions .....	2
1.1 Version 1.1.0.....	2
1.2 Version 1.2.1.....	2
1.3 Version 1.3.0.....	2
1.4 Version 1.3.1.....	2
1.5 Version 1.4.0.....	2

### 1 Firmware versions

#### 1.1 Version 1.1.0

**Bugfix: Sporadic device restart**

#### 1.2 Version 1.2.1

**Change: Nominal zero point for pH sensors**

Range extension: -19.99...19.99 pH

**New: Trace measurement for oxygen sensor SE740**

#### 1.3 Version 1.3.0

**Change: Display of the cell constant of conductivity sensors extended to up to 5 decimal places**

#### 1.4 Version 1.3.1

**New: Live measured values in the toolbar**

**Change: Extension of the setting range for the polarization voltage of analogue oxygen sensors**

The value range has been extended from -1000...-400 mV to -1000...0 mV.

#### 1.5 Version 1.4.0

**Bugfix: Messages P065 and D064 "Sensoface sad cal. timer" changed from class failure to maintenance Requirement**

**Change: Input option flush interval changed from 0.1 h to 0.01 h**